

Example Linux Networking Commands

Terminals, GUIs, run levels, miscellaneous

`startx` (start up gnome desktop)

Alternate command Terminals

`Ctrl-alt-1`

`Ctrl-alt-2`

`Ctrl-alt-3`

`Ctrl-alt-4`

`Ctrl-alt-5`

`Ctrl-alt-6`

Graphical desktop

`Ctrl-alt-7`

`shutdown now`

`init 0` (fastest way to shut down)

`init 1` (minimal system)

`init 3` (normal system)

`su` (gets you to root, without path so must use `\sbin\ifconfig`)

`su -` (gets you to root with root's path)

`/sbin/route -n > myresults` (output overwrites file)

`/sbin/route -n >> myresults` (output appended to file)

Mount external media

`mount /dev/sdal /mnt/usb-stick`

`umount /mnt/usb`

`mount /dev/fd0 /mnt/floppy`

`mount -r -t iso9660 /dev/cdrom /mnt/cdrom`

`umount /mnt/floppy`

`mount /dev/cdrom /mnt/cdrom`

`umount /mnt/cdrom`

To show a running process

`ps -e | grep ppp`

To show parent processes

`ps -ef`

Users and groups (note, new users can't log in without `passwd` used to set password)

`groupadd -g 192 cis192`

`groupdel cis192`

`useradd -g cis192 frank`

`useradd -g users -u 510 sarah`

`id frank`

`passwd frank`

`userdel frank`

 Configuring NICs

`lspci` (gives you hardware clue for which driver to select and install)
`lsmod` (view already installed drivers)

<http://www.tldp.org/HOWTO/text/Ethernet-HOWTO>
<http://www.tldp.org/HOWTO/Hardware-HOWTO/nic.html>

(to research Linux network driver info)

Network drivers (hopefully already in `/lib/modules/2.4.20-8/kernel/drivers/net`)

- `e100` - for Intel Ethernet PRO 100 NIC
- `8139too` - for D-Link NIC with RealTek 8129/8139 chipsets
- `3c59x` - for 3Com 3c905x NICs
- `tulip` - for Lite-on Communications LNE 100TX cards with DEC chipsets

`insmod 3c59x` (installs driver, leave off the `.o` on driver name)
 or `modprobe 8139too` (if driver has dependencies)

`lsmod` (verify new network drive is running)
`/sbin/ifconfig eth1 172.30.4.106 netmask 255.255.255.0 broadcast 172.30.4.255`
 (ifconfig command still classful so must add broadcast)

`/sbin/route add default gw 172.30.4.1` (adds default gateway)

`ifconfig -a` (shows all interfaces)

Other related commands:

`ifconfig lo 127.0.0.1` (configure loopback)
`rmmmod e100` (removes intel NIC driver)
`dmesg` (shows ton of HW info)

`more /var/log/dmesg` (hardware loading info)
`more /proc/modules` (same as `lsmod`)
`more /proc/interrupts` (IRQs)
`more /proc/ioports` (IO ports)

`ifconfig eth0 up`
`ifconfig eth0 down`

`/etc/init.d/network stop`
`/etc/init.d/network start`
`/etc/init.d/network status`

 Configuring client DNS

Edit (`vi` or `gedit`) `/etc/resolv.conf` and add:

`nameserver 207.62.187.54` (IP address of primary name server)
`nameserver XXX.XXX.XXX.XXX` (IP address of secondary name server)

```

search cabrillo.edu          (domain suffix to add for short names)

or echo "nameserver 207.62.187.54" > /etc/resolv.conf

cat /etc/resolv.conf

```

```

Individual hosts can be locally added to the /etc/hosts file
127.0.0.1      donkey localhost.localdomain localhost
192.168.2.106  elrond

```

Configuring NICs permanently

To load NIC driver at system bootup

```

Edit /etc/modules.conf
    To look like:
    alias eth0 8139too
    alias eth1 3c59x
    alias eth1 e100

```

To set IP configuration:

```

Edit /etc/sysconfig/network-scripts/ifcfg-eth0          (or eth1)
    To look like:
    DEVICE=eth0
    USERCTL=no
    ONBOOT=yes
    BOOTPROTO=none
    BROADCAST=192.168.1.255
    NETWORK=192.168.1.0
    NETMASK=255.255.255.0
    IPADDR=192.168.1.5

```

To configure gateway:

```

Edit /etc/sysconfig/network
    To look like:
    NETWORKING=yes
    HOSTNAME=station01.mordor.rivendell.middleearth
    GATEWAY=172.24.1.100
    NISDOMAIN=cismud.net

```

To make static routes permanent:

```

Edit /etc/sysconfig/static-routes
    To look like:
    eth0 host 172.30.4.28 gw 207.62.106.30
    eth0 net 192.168.2.0 netmask 255.255.255.0 gw 172.30.4.107

```

To stop and start network:

```

/etc/init.d/network stop
/etc/init.d/network start
service network restart

```

Watchout for Redhat network utilities which if exist take priority:

```

/etc/sysconfig/networking/profiles/default/
    hosts
    ifcfg-eth0
    ifcfg-eth1
    network
    resolv.conf

```

Cheater baby configuration (watch out for classful broadcasts)

```
netconfig                (TUI wizard for eth0)
netconfig -d eth1       (TUI wizard for eth1)
```

Configuring routes

To display routing table

```
route -n
```

Configure default gateways with:

```
route add default gw 192.168.2.6
route del default gw 192.168.2.6
```

Configure specific routes with:

```
route add -net 192.168.3.0 netmask 255.255.255.0 gw 172.30.4.106
route del -net 192.168.3.0 netmask 255.255.255.0 gw 172.30.4.106
```

```
route add -net 192.168.3.0 netmask 255.255.255.0 dev eth1
route del -net 192.168.3.0 netmask 255.255.255.0 dev eth1
```

Flush the routing table cache:

```
route -CF
```

To enable IP forwarding

```
Echo 1 > /proc/sys/net/ipv4/ip_forward
```

To disable IP forwarding

```
Echo 0 > /proc/sys/net/ipv4/ip_forward
```

To make routing permanent add:

```
Net.ipv4.ip_forward=1 to /etc/sysctl.conf
```

ssh and scp

Copy lab1.txt from remote computer to "here"

```
scp root@172.30.4.106:lab1.txt .
```

Copy a file to Opus


```
scp iptables.simmsr cis192@opus.cabrillo.edu:
scp email cis192@opus.cabrillo.edu:email.simmsr
```

To run a command on a Linux computer and append output to a local file:

```
ssh cis192@opus.cabrillo.edu "quiz simmsr"
ssh root@elrond "route -n" >> results.txt
ssh root@sauron "ping -c3 172.168.4.109" >> results.txt
```

```
scp guest@instructor:/tmp/bind* .
scp guest@gandalf:/tmp/dhcp* /root/
```

ssh port forwarding



To set up a "port forwarding" secure tunnel from an external client's local port 8000 through port 23 on a "firewall" server (172.30.4.107) to a specific internal telnet server (192.168.2.108) use:

```
ssh -L 8000:192.168.2.108:23 172.30.4.107 (on the client)
```

Then to then access the telnet server (192.168.2.108) from the client outside the firewall use:

```
telnet localhost 8000
```

Testing

```
ping -b 172.30.1.255          (broadcast ping)
ping 172.30.4.1              (pings from eth0)
ping -I 192.168.2.106 172.30.4.106 (ping from specific interface ip to remote ip)
ping -c3 172.30.4.107        (ping 3 times only then stop)
```

Note: `ls -l /bin/ping` shows ping in red because it runs as root

```
ethereal          (to run sniffer in GUI)
```

In Ethereal to capture a stream, select a packet then select:
analyze > Follow TCP Stream (from the menus)

Example capture filter to use in the capture setup window:
src host 192.168.2.168 or 172.30.4.110

Example display filter:
ip.src == 15.27.245.100

Monitoring log files on Linux
tail -f /var/log/iptables

Check for installed software

```
rpm -qa | grep telnet
rpm -qa | grep j2sdk
rpm -qa | grep postgres
```

```
rpm -ql dhcp          #files installed by rpm
rpm -ql dhcp          #information on rpm
```

Setup telnet server

```
rpm -qa | grep telnet    (look for telnet-server-0.17-28.i386.rpm)
rpm -ihv telnet-server*
```

To enable telnet server and restrict it to a single client:

```
Modify /etc/xinetd.d/telnet as follows :
# default: on
# description: The telnet server serves telnet sessions; it uses \
#   unencrypted username/password pairs for authentication.
service telnet
{
    flags             = REUSE
    socket_type       = stream
    wait              = no
    only_from         = 192.168.2.107
    user              = root
    server             = /usr/sbin/in.telnetd
    log_on_failure    += USERID
    disable           = no
```

To activate these config file changes

- xinitd can be restarted (slight impact to all services)
 - `/etc/init.d/xinetd restart`
- or touched gently to re-read its config files with
 - `ps -e | grep xinitd` (note *pid* of xinitd procees)
 - `kill -1 pid` (replace "pid" with real pid from previous command)
 - or --
 - `killall -1 xinitd`

iptables firewall

Simple minded firewall wizard:

```
lokkit
```

To remove the older ipchains module:

```
lsmod          (look for ipchains)
rmmod ipchains (if it is there)
```

To view current firewall settings:

```
iptables -L
```

To save and restore firewall tables:

```
iptables-save > iptables.bak    (this is a little weird)
```

```
cat iptables.bak | iptables-restore -c    (this is very weird)
```

To setup firewall to block everything:


```
iptables -P INPUT DROP
iptables -P FORWARD DROP
iptables -P OUTPUT DROP
```

To setup firewall to accept everything:

```
iptables -P INPUT ACCEPT
iptables -P FORWARD ACCEPT
iptables -P OUTPUT ACCEPT
```

To flush rules:

```
iptables -F
```



Celebrian configuration:

New connections from within firewall OK

```
iptables -A FORWARD -s 192.168.2.0/24 -d 0/0 -m state --state NEW -j ACCEPT
```

External packets to our Telnet server on port 23 OK

```
iptables -A FORWARD -s 0/0 -d 192.168.2.108 -m state --state NEW,ESTABLISHED,RELATED -p tcp --dport 23 -j ACCEPT
```

Already established and related traffic OK

```
iptables -A FORWARD -m state --state ESTABLISHED,RELATED -j ACCEPT
```

OK for firewall to output packets

```
iptables -A OUTPUT -m state --state NEW,ESTABLISHED,RELATED -j ACCEPT
```

OK for firewall to accept packets from internal servers:

```
iptables -A INPUT -i eth0 -s 192.168.2.0/24 -d 192.168.2.107 -m state --state NEW -j ACCEPT
```

```
iptables -A INPUT -m state --state ESTABLISHED,RELATED -j ACCEPT
```

To allow gedit to work (which need loopback):

```
iptables -A INPUT -I lo -j ACCEPT
```

```
-----
iptables NAT
-----
```

To load NAT iptables module

```
modprobe iptable_nat
```

Create a pseudo public address (with IP aliasing) for external telnet server access
`ifconfig eth1:0 172.30.4.5 netmask 255.255.255.0 broadcast 172.30.4.255`

Translate incoming pseudo destination address to the telnet server:
`iptables -t nat -A PREROUTING -d 172.30.4.5 -j DNAT --to-destination 192.168.2.108`

Translate outgoing packet source addresses from the internal telnet server to the pseudo address
`iptables -t nat -A POSTROUTING -s 192.168.2.108 -j SNAT --to-source 172.30.4.5`

Translate other outgoing packets from other internal servers to have source IP of firewall public address
`iptables -t nat -A POSTROUTING -s 192.168.2.0/24 -j SNAT --to-source 172.30.4.107`

iptables logging

edit `/etc/syslog.conf` and add `kern.info /var/log/iptables` near top

`more /etc/syslog.conf` (to check if vi edits worked)

`> /var/log/iptables` (to create empty log file)

`service syslog restart` (to restart logging)

to log INPUT and FORWARD entries

`iptables -A INPUT -j LOG --log-level info --log-prefix "iptables INPUT: "`


`iptables -A FORWARD -j LOG --log-level info --log-prefix "iptables FORWARD: "`

`tail -f /var/log/iptables` (to monitor log)

VI commands (when desparate and gedit is not available)

j = scroll down
k = scroll up
l = scroll right
i = input mode
dd = delete line
o = start input mode after this line
esc = go to command mode
:w! = exit and save
:q! = quit without saving
x = delete

Setting up a serial connection



Part I - set up the server (Elrond):

```
ls -l /dev/ttyS?      (lists the serial devices ttyS0 to ttyS9)
setserial /dev/ttyS0 (shows UART, port and IRQ for COM 1)
/etc/inittab         (used by INIT process for specific run level)
```

Note: want UART to be 16550A for high speed connection

The following entry is placed near the end of the `/etc/inittab` file. It will respawn (restart) `agetty` which is used to open the specified tty port and initiate a login:

```
s1:35:respawn:/sbin/agetty 38400 ttyS0
```

```
telinit q          (tells init to re-examine the updated /etc/inittab file)
chmod u+s /usr/sbin/pppd (permission change so normal users run pppd)
```

Part II - set up the client (Frodo) and login to the server (Elrond):

```
minicom -s (to reconfigure minicom for /dev/ttyS0 instead of /dev/ttyS1
default)
minicom -o (to run the terminal emulator for logging into Elrond, -o
suppresses modem commands)
```

Minicom provides terminal emulation and modem control. It is initially used on Frodo to login into Elrond over the serial cable as any terminal would log into a mini-computer. Note use `TERM=ansi77` if not running from an xterm (i.e. gnome desktop).

Part III - using pppd for layer 2 part of network connection

Pppd functions as both a server and client on both ends to create the pppd network connection over the same serial link. This results in ppp0 interfaces showing up in ipconfig output. We need a way to get pppd to run when login in to the server (Elrond) from the client (Frodo). To do this we put the following pppd command into the Elrond's `/home/guest/.bash_profile` so it will run someone logs into Elrond's guest account:

```
/usr/sbin/pppd -detach crtscts proxyarp 10.0.0.1:10.0.0.2 /dev/ttyS0 38400
```

Note on pppd options and args:

```
-detach - keeps init from continuously spawning new instances of pppd
crtscts - use HW flow control
proxyarp - provides arp functionality to work with other Ethernet LANs
10.0.0.1:10.0.0.2 - local gets 10.0.0.1, remote peer (Frodo) gets 10.0.0.1
38400 - baud rate
```


On the client Frodo, we use

```
minicom -o (to login to Elrond, -o suppresses modem commands)
Ctrl-A z q (to quit minicom)
```

```
pppd -detach crtscts /dev/ttyS0 38400 & (preload this, needs fast typing)
```

At this point we have a network connection with ppp0 interfaces showing on both ends with the ip addresses shown above being used. Routing and IP forwarding can be set up as with any other network.

Automating a serial connection



To create a user on Elrond server that uses the pppd command as the shell use:

```
useradd -u 100 -g 100 -c "PPP Account" -d /etc/ppp -s /usr/sbin/pppd ppp
passwd ppp (to set the password for user ppp)
```

On Elrond, put the following options for the pppd daemon in the `/etc/ppp/options` file:

```

-ddetach (stop spawning additional pppd processes)
crtscts (use HW flow control i.e. RTS/CTS)
lock (exclusive access to serial port)
proxyarp (arp handling for coexisting with Ethernet LAN's )
10.0.0.1:10.0.0.2 (local:remote IP addresses to configure)
/dev/ttyS0 (serial port to use)
38400 (baud rate)

```

On the client Frodo create the following `ppp-on` script:

```

pppd updetach crtscts defaultroute /dev/ttyS0 38400 connect \
"exec chat -v TIMEOUT 3 ogin:--ogin: ppp assword: secret"
updetach
updetach - pppd will detach once connection is established
defaultroute - adds static default route using peer as the gateway
\ - negates the carriage return to get this all on one line
connect - runs the script that follows
"exec chat ..." - script using chat command to login to ppp user account
Chmod 7555 ppp-on (makes script executable)
./ppp-on (runs script)

```

At this point we have a network connection with ppp0 interfaces showing on both ends with the ip addresses shown above being used. Routing and IP forwarding can be set up as with any other network.

Install firefox

www.mozilla.org and download latest
`tar -xzvf firefox-1.5.0.2.tar.gz`
`cd firefox`
`./firefox`

To update task bar icon
Right-click on WWW icon on taskbar
Change to firefox in firefox directory

 Samba

RPMs:

```
samba-common-*
samba-client-*
samb-*
samba-swat-*
```

(Install common first)

```
rpm -ihv samba-common-*      #to install
rpm -qi samba                 #to query installed rpm
rpm -qa | grep samba         #to see what rpms are installed
```

Configure /etc/samba/smb.conf

```
workgroup = WORKGROUP
server string = Cool Virtual Samba Server
hosts allow = 192.168.2. 172.30.4. 127.
encrypt passwords = yes
smb passwd file = /etc/samba/smbpasswd
```

Add share definitions to end of config file:

```
[var]
comment = Linux Log files
path = /var
writable = yes
browseable = yes
hide dot files = yes
guest ok = yes
```

To check smb.conf for errors

```
testparm
```

Add a shared user

```
smpasswd -a cis192           #to add user
smbpasswd -x cis192         #to delete user
```

```
service smb start
service smb stop
service smb restart
```

```
smbclient -L celebrian -U cis192%password      #to see shares
smbclient -L frodo -U cis192%password
```

```
mount -t smbfs -o username=cis192,password=cis192 #to mount share
//frodo/SharedDocs /mntpoint
```

```
-----
DHCP
-----
```

```
rpm -ihv dhcp-3.0pl2-6.14.i386.rpm
```

Configure DHCP:

```
vi /etc/dhcpd.conf
touch /var/lib/dhcpd/dhcpd.leases
```

```
[root@celebrian root]# cat /etc/dhcpd.conf
ddns-update-style interim;
ignore client-updates;
option time-offset                -25200; # Pacific Daylight Time
#
# R I V E N D E L L
#
subnet 192.168.2.0 netmask 255.255.255.0 {
    option routers                192.168.2.107; # Default GW
    option subnet-mask           255.255.255.0;
    option domain-name           "Rivendell";
    option domain-name-servers   207.62.187.54;

    range dynamic-bootp         192.168.2.50 192.168.2.99;
    default-lease-time          21600;
    max-lease-time              43200;

    # give the relay agent a fixed address
    host Arwen {
        hardware ethernet       00:03:FF:9E:8E:68;
        fixed-address            192.168.2.150;
    }
}
#
# S H I R E
#
subnet 172.30.4.0 netmask 255.255.255.0 {
    option routers                172.30.4.1;
    option subnet-mask           255.255.255.0;
    option domain-name           "Shire";
    option domain-name-servers   207.62.187.54;

    range dynamic-bootp         172.30.4.50 172.30.4.99;
    default-lease-time          21600;
    max-lease-time              43200;
}
#
# M O R D O R
#
subnet 192.168.3.0 netmask 255.255.255.0 {
    option routers                192.168.3.150;
    option subnet-mask           255.255.255.0;
    option domain-name           "Mordor";
    option domain-name-servers   207.62.187.54;

    range dynamic-bootp         192.168.3.50 192.168.3.99;
    default-lease-time          21600;
    max-lease-time              43200;
}
[root@celebrian root]#
```

Start and stop DHCP:

```
service dhcpd start
service dhcpd stop
service dhcpd restart
service dhcpd status
```

```
ps -e | grep dhc
```

```
/var/lib/dhcp/dhcpd.leases      (server lease log)
```

To permanently run when computer boots up:

```
chkconfig --level 35 dhcpd on
```

```
chkconfig --list dhcpd
ls /etc/rc.d/rc3.d/
```

Configure DHCP relay agent:

```
vi /etc/sysconfig/dhcrelay
INTERFACES="eth0 eth1"      (one for server, one for clients)
DHCPSEVER=192.168.2.107
```

Stop and start DHCP relay agent:

```
service dhcrelay start
service dhcrelay stop
service dhcrelay restart
```

```
ps -e | grep dhc
```

DHCP client :

```
dhclient                      (request IP address)
dhclient -r                   (release IP address)
/var/lib/dhcp/dhclient.leases  (client lease log)
```

```
-----
DNS Server
-----
```

Check for and install DNS

```
rpm -qa | grep bind
rpm -qa | grep bind-utils
rpm -qa | grep caching
```

```
rpm -ihv bind-9.2.2-21.i386.rpm
rpm -ihv caching-nameserver-7.2-7.noarch.rpm
```

DNS configuration

```
/etc/named.conf (overall config file)
```

```
[root@arwen root]# cat /etc/named.conf
// generated by named-bootconf.pl

options {
    directory "/var/named";
    /*
     * If there is a firewall between you and nameservers you want
     * to talk to, you might need to uncomment the query-source
     * directive below. Previous versions of BIND always asked
     * questions using port 53, but BIND 8.1 uses an unprivileged
     * port by default.
     */
    // query-source address * port 53;
};

//
// a caching only nameserver config
//
controls {
    inet 127.0.0.1 allow { localhost; } keys { rndckey; };
};
zone "." IN {
    type hint;
    file "named.ca";
};

zone "localhost" IN {
    type master;
    file "localhost.zone";
    allow-update { none; };
};

zone "0.0.127.in-addr.arpa" IN {
    type master;
    file "named.local";
    allow-update { none; };
};

zone "rivendell" {
    type slave;
    file "db.rivendell";
    masters {192.168.2.107; };
};
```

```
include "/etc/rndc.key";
[root@arwen root]#
```

`/var/named/db.rivendell` (one of the zone files)

```
[root@celebrian root]# cat /var/named/db.rivendell
$TTL 604800
; Rivendell Zone Definition
;
;
Rivendell.      IN SOA hostname.rivendell. root.rivendell. (
                2001080109      ;      serial number
                60              ;      refresh rate in seconds
                15              ;      retry in seconds
                1209600         ;      expire in seconds
                300)            ;      minimum in seconds
;
;
;
;Name Server Records
Rivendell.      IN NS hostname.rivendell.
;
;Address Records
localhost      IN A    127.0.0.1
legolas        IN A    192.168.2.105
elrond         IN A    192.168.2.106
celebrian      IN A    192.168.2.107
arwen          IN A    192.168.2.108
galadriel      IN A    192.168.2.104
;
;CNAME records
```

`named-checkconf` (checks DNS files)

Operation

```
rndc reload      #reloads zone files
rndc flush       #flushes cache
```

Start and stop DNS

```
service named start
service named stop
service named restart
```

```
chkconfig --level 35 named on      #always start at bootup
```

```
ps -e | grep named                  #check if DNS service running
```

Monitor DNS log file

```
tail -f /var/log/messages
```

DNS utilities

```
host Legolas
dig @celebrian legolas
```

 NFS

`rpm -q portmap nfs-utils`

To access shares on remote computers:

```

showmount -e hershey                #show available mounts on hershey

Temporary
mount hershey:/home/cis192 /home    #mount remote share to local directory
mount                               #to verify
umount /home                       #unmount share

mount shadowfax:/home/cis192/images /tmp/images

Permanent
Edit /etc/fstab and add:
    hershey:/home/cis192 /home nfs defaults 0 0

    mount                            #to verify

```

To make shares for others

```

Edit /etc/exports file and add:
    /home/cis192 192.168.2.0/255.255.255.0(ro,no_root_squash,sync)
    /home/guest  *(rw,sync)

service nfs start

exportfs -rv                        #after modifying /etc/exports

```

NIS

NIS client

domainname cismud.net

- or -

Add "NISDOMAIN=cismud.net" to /etc/sysconfig/network

Configuration files

/etc/nsswitch.conf

```
#hosts:      db files nisplus nis dns
hosts:      dns files nis
```

/etc/yp.conf file

```
service ypbind start
service ypbind status
```

Configure ypbind to start automatically on boot:

```
chkconfig --level 35 ypbind on
chkconfig --list
chkconfig --list ypbind
```

NIS Server

```
ypserv is the daemon
/etc/ypserv.conf is config file
/var/yp has makefile and map files
  Host.byaddr
  Hosts.byname
  hosts
```